

Electric Transmission Tax (TB)

Pipe "|" Delimited File Layout

Field Number	Field Name	Field Type	Description
1	Year	String	Four Digit Year
2	File Type	String	Value should be "TB". Determines type of file
3	County Number	String	Two Digit County Code
4	County Name	String	Name of County where the transmission originated*
5	City Name	String	Name of City where the transmission originated*
6	Township Number	Numeric	Township number in PLSS legal description where transmission originated**
7	Township Name	String	Name of Township where the transmission originated*
8	Range Number	Numeric	Range number in PLSS legal description where transmission originated**
9	Section Number	Numeric	Section number in PLSS legal description where transmission originated**
10	School District	String	School district where transmission originated
11	Fire District	String	Fire District where transmission originated
12	Other Tax District	String	Other Tax District
13	Other Tax District 2	String	Other Tax District
14	Year In Service	String	Four Digit Year. Year the Transmission line became active after 1/1/2009. If prior to 1/1/2009 enter 1900. All cells must contain a four digit year.
15	Line Voltage (kv)	Decimal	Kilovolts in numeric form. May contain decimal***
16	Schedule Number	Numeric	Numeric Value to determine the TB schedule being uploaded (Schedules 1-4)
17	Less than 50 kv	Decimal	Mileage of line less than 50 kilovolts****
18	50 kv-99 kv	Decimal	Mileage of line between 50 kilovolts and 99 kilovolts****
19	100 kv-199 kv	Decimal	Mileage of line between 100 kilovolts and 199 kilovolts****
20	200 kv-229 kv	Decimal	Mileage of line between 200 kilovolts and 229 kilovolts****
21	200 kv-299 kv	Decimal	Mileage of line between 200 kilovolts and 299 kilovolts****
22	230 kv or more	Decimal	Mileage of line 230 kilovolts or greater****
23	300 kv or more	Decimal	Mileage of line 300 kilovolts or greater****
24	Percentage Owned	Decimal	Percentage of transmission line owned by company. May contain decimal**

* Either a Township Name or a City Name can be used per record. Using both a township and city on a record will not be allowed.

**Only numbers will be allowed on these fields.

***Kilovolts field. NUMERIC VALUES ONLY. Do not enter dollar signs. Commas are ok and only accept one (1) decimal point. Negative values must start with the Hyphen "-".

****Mileage fields. NUMERIC VALUES ONLY. RECORD ONE CIRCUIT/LINE PER ROW. (69/115 will not be accepted.) MAY ONLY ENTER MILEAGE FOR ONE KILOVOLT LINE PER ROW. Commas are ok and six (6) decimal points are accepted. Negative values must start with the Hyphen "-".